



# BURN CD-Rs

## MULTI-SESSION

WITH APPLE MACINTOSH COMPUTERS

© May 23<sup>rd</sup>, 2006

*These instructions will teach you how to burn Multi-session CDs using Disk Utility on Apple Macintosh Computers*

### OVERVIEW

Normally, you can only burn on a *CD-R disc once*. This paper will teach you how to burn data on *CD-R disc more than once*, assuming space is available on the disc. If you use Disk Utility in Mac OS X to burn the disc, you can set it up for "multi-session" burning so that you can burn more disc images on the disc in the future.

### ATTENTION:

If you are not concerned about burning more than once on a CD-R, you do not need to follow these instructions. Please refer to "How to Burn CDs" document.

### WARNING

The Data that is burned on a CD using this tutorial will not be accessible on a PC.

### Burning


*Step 1 – Put all your eggs in one basket!*

Collect all of your data together and place it in a folder on the Desktop.

*Step 2 – Open Disk Utility*

In finder, from the menu bar choose GO > "Utilities" and open the "Disk Utility" application.

In Disk Utility, choose File > New > "Disk Image from Folder".





# BURN CD-Rs


## MULTI-SESSION

WITH APPLE MACINTOSH COMPUTERS

© May 23<sup>rd</sup>, 2006


These instructions will teach you how to **burn Multi-session CDs** using **Disk Utility** on **Apple Macintosh Computers**

In the dialogue box select the folder you created on Desktop and click *Image*.



### Step 3 – Make a Disk Image (.dmg File)

In the *Save As:* field, specify a name for your disk image;  
In the image format drop-down menu choose “*compressed*”;  
In the Encryption drop-down menu choose “*none*”;  
Click *Save*.





# BURN CD-Rs


## MULTI-SESSION

WITH APPLE MACINTOSH COMPUTERS


© May 23<sup>rd</sup>, 2006

These instructions will teach you how to burn Multi-session CDs using Disk Utility on Apple Macintosh Computers

### Step 4 – It tastes like burning...


When the disk image is complete after the processing, choose it by clicking on it in the Disk Utility list on the left frame and then click 

Insert a blank CD in the optical drive. (If you do not see the window below, click on the triangle in the top-right corner)

Select the "Leave disc appendable" checkbox. Afterwards, click .



To open the CD drive hold down the Eject button on the top-right corner of the keyboard until it opens.



To add disk images to the disc later, follow the steps above to create a new disk image and burn it to the disc. You can continue this process until all available space on the disc is used.